


CADD RESOURCES AVAILABILITY

Date: June 1st, 2020

RE: CADD Resources Availability

To: All CADD Users

Effective immediately, the method to access the Delaware Department of Transportation (DeDOT) CADD resources, via the online ProjectWise interface, will be through the new **ProjectWise Web View**.



Using **ProjectWise Web View** requires all users to have a registered account with Bentley Systems prior to attempting to access the CADD resources. Most users currently utilizing the Bentley products already have an account and do not need to create a new account. If you sign in through the Bentley Connection Client interface, you have an account. **If you are working for a company that has a Bentley Account Administrator, then your company's Bentley Account Administrator must add the DeDOT ProjectWise datasource before other users can access the DeDOT ProjectWise datasource.**

If you do not have an account with Bentley Systems, there is no charge to create an account with Bentley Systems.


Once you have a registered account with Bentley Systems, you are required to send an email to DOT_CADDSupport@delaware.gov requesting access to the DeDOT CADD Standards. Please provide the email address linked to the Bentley Systems account so that we can provide you access. **Please verify that you are sending the correct email address, which is the email address tied to your Bentley Systems account.**

CADD RESOURCES AVAILABILITY


Once your account has been added to the DelDOT ProjectWise system, you can access the DelDOT CADD standards with the following method.

Access ProjectWise Web View

- Right-click on the Connection Client icon in your computers task list (Lower-right corner), and select the CONNECT Center menu item from the list that appears.



- On the CONNECT Center webpage that appears, click the **Services** icon (3x3 tiles) in the upper-left corner of the menu bar, and scroll down to until you see the **ProjectWise Web View** under the **My Services** Section.




CADD RESOURCES AVAILABILTY

If the **DeIDOT PW** datasource does not appear under the **Datasources** column, you will need to add the datasource utilizing the following steps:

(Performed By Your Bentley Account Administrator where Applicable)

- 1) Select **Manage Connections**.
- 2) Select the **New Connection** button.
- 3) In the **Create New Connection** dialog, enter the following information:
 - **Connection Name:** DeIDOT PW
 - **Server URL:** <https://deldot-pw-ws.bentley.com/ws>
- 4) Select the Get Datasource button.



Create New Connection

Connection Name
DeIDOT PW

Server Url
https://deldot-pw-ws.bentley.com/ws


Get Datasource

Datasource

Description
Description

Connect Cancel

- 5) The drop-down list under **Datasource** becomes active. Select **DELDOT Production** from the list.



Create New Connection

Connection Name
DeIDOT PW

Server Url
https://deldot-pw-ws.bentley.com/ws

Get Datasource


Datasource
Select...
DELDOT Testing
DELDOT Production

Connect Cancel


- 6) Enter a **DeIDOT Production** in the **Description** field, and select the **Connect** button.

CADD RESOURCES AVAILABILITY

7) The **DeIDOT PW** connection will show in the list if everything was successful.



8) Under the **Datasources** column, select the new connection you just made to show the contents of the **DeIDOT PW** datasource and then select the “02 Standards” folder to access the DeIDOT CADD Standards.



9) There are currently two files provided for your use:

- **DeIDOT_CONNECT_Standards.zip** – DeIDOT MSCE and ORD CADD standards.
- **InRoads_SS10_Standards.zip** – DeIDOT MSv8 and Power Inroads SS10 CADD Standards.

Each file has a readme text file contained inside, along with installation instructions. All issues, comments, and recommendations should be directed to DOT_CADDSupport@delaware.gov.